

VMD Tutorial

Source: <https://www.ks.uiuc.edu/Training/Tutorials/vmd-index.html>

Unit 1: Introduction

1. Download the pdb file of Ubiquitin (1UBQ.pdb)
2. To load, "New Molecule" → "Browse" → "Load"
3. Hotkeys

c	Center: Change rotation point by clicking on an atom. Reset to default with Reset View.
0	Query: Click on an item to print its name in the console.
1	Label → Atom: Toggle atom label on/off by clicking on an atom.
2	Label → Bond: Toggle bond distance label by clicking on two atoms in sequence.
3	Label → Angle: Toggle angle label by clicking on three atoms in sequence.
4	Label → Dihedral: Toggle dihedral angle label by clicking on four atoms in sequence.
5	Move → Atom: Change atom position by clicking and dragging the atom.
6	Move → Residue: Move all atoms in a selected residue by dragging one atom. Shift key rotates about selected atom; middle button rotates about a line through the atom.
7	Move → Fragment: Move all atoms in a selected fragment similarly to residues.
8	Move → Molecule: Move all atoms in a selected molecule by dragging one atom.
9	Move → Rep: Move atoms in a selected representation by clicking on an atom within that rep.

4. Representation style

Lines	simple lines for bonds, points for atoms
Bonds	lighted cylinders for bonds
DynamicBonds	dynamically calculated distance-based bonds
HBonds	display hydrogen bonds
Points	just points for atoms, no bonds
VDW	atom as sphere
CPK	ball & stick model
Licorice	ball & stick model, radius cannot be changed
Polyhedra	polyhedra connecting atoms within a cutoff radius
Trace	connected cylindrical segments through C alpha atoms
Tube	smooth cylindrical tube through the C alpha atoms
Ribbons	flat ribbon through the C alpha atoms
NewRibbons	smooth ribbon through the C alpha atoms
Cartoon/ NewCartoon	secondary structure: helices=cylinders, beta-sheets=solid ribbons, other=tube
PaperChain	display ring structures as polygons, colored by ring pucker

Twister	flat ribbon tracing glycosidic bonds, with twists oriented by sugar residues
QuickSurf	molecular surface (Gaussian density surface)
MSMS	molecular surface as determined by the program MSMS
Surf	molecular surface as determined by SURF
VolumeSlice	display a texture mapped slice from a volumetric data set
Isosurface	display an isovalue surface from a volumetric data set
FieldLines	field lines generated by integrating particles by volume gradient vectors
Orbital	molecular orbital selected by wavefunction type, spin, excitation, and orbital ID
Beads	per-residue approximate bounding spheres
Dotted	dotted van der Waals spheres for atoms, no bonds
Solvent	dotted representation of the solvent accessible surface

5. Color categories

Display	Color of background, gradient, depth cueing, text
Axes	The components of the axes
Name	The available atom names (color by Name)
Type	The available atom types (color by Type)
Element	Atomic elements (color by Element), with "X" for unknown
Resname	The residue names (color by ResName)
Restype	The residue types - non-polar=white, basic=blue, acidic=red, polar=green
Chain	The one-character chain identifier.
Segname	The segment names (color by SegName)
Conformation	The available conformation codes (color by Conformation)
Molecule	The names assigned to each molecule (color by Molecule)
Highlight	The protein, nucleic, and non-backbone colors
Structure	The secondary structure type (helix, sheet, coil) (color by Structure)
Surface	The surface types
Labels	The different labels (atoms, bonds, etc.)
Stage	The colors for the checkboard stage

6. Select atoms by typing “Singlewords” in “Selected Atoms”

- a. And, or, not
- b. “Keyword”

7. View sequence in “Sequence Viewer”, color code obtained from STRIDE

- a. B-value = temperature factor
- b. Struct = secondary structure

T	Turn
E	Extended conformation (β sheets)
B	Isolated bridge
H	Alpha helix
G	3-10 helix
I	Pi helix
C	Coil

8. Save visualisation state: "File" → "Save State" (.vmd)
9. Change background: "Graphics" → "Colors" → "Display" → "Background"
10. Rerender image: "File" → "Render" → "Render using" → "TachyonInternal" (.tga)

Unit 2: Multiple Molecules and Scripting

Description:

- Experiment: Equilibration simulation of ubiquitin
- Medium: Water
- Duration: 1 ns
- Task: Compare conformation of ubiquitin at the end of this simulation with the initial crystal structure

1. Download the pdb file of Ubiquitin {1UBQ.pdb} → Rename to "crystal"
2. "New Molecule" → "Browse" → "Load"
3. Add the structure file containing Ubiquitin at the end of simulation {ubiquitin.psf} to "New Molecule"
4. Add the coordinate file at the end of simulation {ubiquitin-equilibrated.coor} to "ubiquitin.psf" → Rename to "simulation"
5. Unfix both molecules (F in red) and "Reset View"
6. Only display the "crystal" molecule (D in black)
7. Set "crystal" molecule as top (T)
8. "Extensions" → "Tk Console"

Commands	set crystal [atomselect 0 "all"]	Set all atoms in molecule 0 as "crystal"
	\$crystal num	Obtain the number of crystal
	\$crystal set beta 0	Set "crystal" as beta 0
	\$crystal get resname	
	set M [measure fit \$alpha1 \$alpha2]	Transformation matrix M that map first selection onto second
	\$crystal move \$M	

	atomselect macro bstrand1 {protein and resid 2 to 6}	Create macro for bstrand1 including residues 2 to 6, found in Selections > singlewords																		
	source filename.tcl	Import source code																		
Selection methods with “”	all	All atoms																		
	hydrophobic																			
	alpha	alpha carbon																		
	<table><tr><th colspan="2">Some Common Atom Selections</th></tr><tr><th>Atom Selection</th><th>Description</th></tr><tr><td>all</td><td>Show all atoms</td></tr><tr><td>protein</td><td>Show only protein atoms</td></tr><tr><td>backbone</td><td>Displays backbone atoms</td></tr><tr><td>noh</td><td>Do not display hydrogen atoms</td></tr><tr><td>resname X</td><td>Displays atoms of residue X</td></tr><tr><td>name X</td><td>Display atoms named X</td></tr><tr><td>resid X</td><td>Display residue number X</td></tr></table>	Some Common Atom Selections		Atom Selection	Description	all	Show all atoms	protein	Show only protein atoms	backbone	Displays backbone atoms	noh	Do not display hydrogen atoms	resname X	Displays atoms of residue X	name X	Display atoms named X	resid X	Display residue number X	
Some Common Atom Selections																				
Atom Selection	Description																			
all	Show all atoms																			
protein	Show only protein atoms																			
backbone	Displays backbone atoms																			
noh	Do not display hydrogen atoms																			
resname X	Displays atoms of residue X																			
name X	Display atoms named X																			
resid X	Display residue number X																			
Display methods	beta 0																			
	radius 1.5																			
Obtain information	resname	Residual name																		
	resid	Residual index																		
	index	Atom index																		
	name	Atom name																		
	{x y z}	Coordinates																		
file	psf	Protein structure																		
	vmd	Status																		
	dcd	Trajectory																		
	tcl	Text script																		

9. Display both molecules (D in black)
10. For both crystal and simulation, set coloring method to "ColorID" and "0 blue" and "1 red" respectively, drawing method to "Tube"
11. In Tk Counsole window, select the protein backbone of both proteins
 - a. set alpha1 [atomselect 0 "alpha"]
 - b. set alpha2 [atomselect 1 "alpha"]
12. Calculate and apply transformation matrix M to best map alpha2 to alpha1
 - a. set M [measure fit \$alpha1 \$alpha2]
 - b. set crystal [atomselect top "all"]
 - c. \$crystal move \$M
13. Run pre-written script to compare atoms' positions

a. source coloring.tcl

```
(input) 55 % source coloring.tcl
-1.4344735145568848 1.5170034170150757 -11.387672424316406, -1.8203625679016113
1.046593189239502 -11.700506210327148
-1.4344735145568848 - -1.8203625679016113
-1.2171720266342163 4.893920421600342 -9.64897632598877, -1.5955531597137451 4.4
61385726928711 -10.035935401916504
-1.2171720266342163 - -1.5955531597137451
-2.2546496391296387 5.21519660949707 -6.0121073722839355, -2.407890558242798 4.8
41493606567383 -6.30332612991333
-2.2546496391296387 - -2.407890558242798
-2.1305925846099854 8.245089530944824 -3.6896939277648926, -2.268209218978882 8.
021492004394531 -4.130740642547607
-2.1305925846099854 - -2.268209218978882
-0.6730284690856934 8.250974655151367 -0.16197004914283752, -0.6497521996498108
8.03714656829834 -0.564492404460907
-0.6730284690856934 - -0.6497521996498108
-1.9813416004180908 11.187929153442383 1.9380509853363037, -1.056281328201294 11
.034486770629883 1.8269755840301514
-1.9813416004180908 - -1.056281328201294
```

<pre># Define the coloring procedure: proc tutorialcoloring {} { # Get the molIDs of the first 2 molecules. set mol1 [lindex [molinfo list] 0] set mol2 [lindex [molinfo list] 1] # Create our two sels set sel0 [atomselect \$mol1 "alpha and protein"] ;# crystal set sel1 [atomselect \$mol2 "alpha and protein"] ;# simulation # Create an empty list (for all the displacements) set mylist {}</pre>	<pre># loop over the position vectors v1 and v2 for each atom: foreach v0 [\$sel0 get {x y z}] v1 [\$sel1 get {x y z}] { puts "\$v0, \$v1" puts "[lindex \$v0 0] - [lindex \$v1 0]" set dx [expr [lindex \$v0 0] - [lindex \$v1 0]] set dy [expr [lindex \$v0 1] - [lindex \$v1 1]] set dz [expr [lindex \$v0 2] - [lindex \$v1 2]] # Calculate displacement for a given atom set disp [expr (\$dx*\$dx + \$dy*\$dy + \$dz*\$dz)] lappend mylist \$disp } # Assign the displacements to beta values of the crystal molecule \$sel0 set beta \$mylist } # Run the procedure here tutorialcoloring</pre>
--	--

14. For “crystal” molecule, change Coloring Style to “Beta”


15. Hide “simulation” molecule

16. “Graphical Representations” → “Trajectory” → “Color Scale Range” → “crystal” → “0””5”
(A) → “Set”

17. “Graphics” → “Colors” → “Color Scale” → “Method” → “BWR” low displacement=blue;
high displacement=red, in between=white

18. Shift “Midpoint” to 0.1


19. Output as {1ubq-equilibration-in-water.vmd}



Unit 3: Trajectories, Macros and Labels


Description:

- FMA experiment
- 1. Add frames {pulling.dcd} to equilibrated structure file {ubiquitin.psf} → “Load”
- 2. Go to the first frame
- 3. Drawing Method = “Tube”; Selected Atoms = “protein”
- 4. “Create Rep” → Drawing Method = “Lines”; Selected Atoms = “water” → Turn off representation
- 5. To create macros of each strand in the mixed beta sheet, in Tk Console
 - a. atomselect macro bstrand1 {protein and resid 2 to 6 }
 - b. Repeat for the rest of the strands
 - c. Sequence of each beta strand can be found in “Sequence Viewer”, coloured in yellow
- 6. To create a representation with the 3rd and 5th beta strands, “Create Rep” → “Selected Atoms” → “Selections” → “Sinlewords”: “bstrand3 or bstrand5” → Draw Style = “Cartoon”, yellow
- 7. Create the representation with bstrand1,2,4. As bstrand4 only has two residues, it is not shown




- 8. Change “protein” to “protein and not betasheet”
- 9. To see the features of ubiquitin unfolding, “Create Rep” → “Selected Atoms”= ”betasheet and backbone” → Draw Style = “Hbonds”; Drawing Method = “Color ID”, red; Distance

Cutoff = "3.2"; Angle Cutoff = "30"; Line Thickness "5"




10. "File" → "Save State" (.vmd)
11. Use the slider to obtain the shape of protein and surrounding water molecules at different times
12. To label bonds or atoms, "Mouse" → "Label" → "Atoms"
 - a. To remove labels, "Graphics" → "Labels" → "Delete"
13. To make VDW Representation for alpha carbon of Lysine 48 and of the C terminus
 - a. (Tk console) Set sel [atomselect top "resid 48 76 and name CA"]
 - b. (Tk console) \$sel get index >> "770 1242"
 - c. Create VDW Representation with selection index 770 1242
 - d. Label the 2 atoms



e. “Graphics” → “Labels” → “Bonds” → “Graph” (.dat)


```
In[18]:= data = Import["/Users/heiley/Desktop/SURP/vmd-tutorial/output/2-lubq-AFM-length.dat"];
Choose new cell type
In[19]:= plot = ListPlot[data, Joined → True, PlotLabel → "Bond Length in AFM Experiment", LabelStyle → "Black,Bold"]
```



```
In[16]:= Export["/Users/heiley/Desktop/SURP/vmd-tutorial/output/2-lubq-AFM-length.png", plot]
Out[16]:= /Users/heiley/Desktop/SURP/vmd-tutorial/output/2-lubq-AFM-length.png
```


14. To calculate RMSD of equilibration trajectory

- “Molecule” → “Delete Frames”
- “File” → “Load Data to Molecule” {equilibration.dcd}
- Turn on water representation
- (Tk console) source rmsd.tcl



e. Generate graph using {rmsd.dat}

```
In[19]:= data = Import["/Users/heiley/Desktop/SURP/vmd-tutorial/output/3-lubq-equilibration-evolution-rmsd.dat"];
In[20]:= plot = ListPlot[Flatten[data], Joined → True, PlotLabel → "RMSD Of Equilibration Trajectory", LabelStyle → "Black,Bold"]
```



```
In[21]:= Export["/Users/heiley/Desktop/SURP/vmd-tutorial/output/3-lubq-equilibration-evolution-rmsd.png", plot]
Out[21]:= /Users/heiley/Desktop/SURP/vmd-tutorial/output/3-lubq-equilibration-evolution-rmsd.png
```


- f. {rmsd-fullthrottle.tcl} calculates the average RMSD for each residue in a selection over all frames in a trajectory



More RMSD. You can try sourcing another script called `rmsd-fullthrottle.tcl`. Take a look at this script to learn simple procedures in tcl, as well as calculating the RMSD of each residue over time and coloring residues according to their RMSD similarly that in Unit 2.

```
VMD TkConsole

RMSD of residue 49 is 11.315936614333847
RMSD of residue 50 is 7.376574008093204
RMSD of residue 51 is 7.139769707197025
RMSD of residue 52 is 5.660482714389578
RMSD of residue 53 is 3.6230142885520134
RMSD of residue 54 is 4.208507551455203
RMSD of residue 55 is 2.385561536675618
RMSD of residue 56 is 1.7846946009883173
RMSD of residue 57 is 2.839355844774364
RMSD of residue 58 is 3.5910484069659385
RMSD of residue 59 is 3.002288983559903
RMSD of residue 60 is 2.4853375763804824
RMSD of residue 61 is 1.8438004641621202
RMSD of residue 62 is 3.802000853014581
RMSD of residue 63 is 3.5481538787300204
RMSD of residue 64 is 3.9531337891095952
RMSD of residue 65 is 3.482671253475142
RMSD of residue 66 is 3.47489579849773
RMSD of residue 67 is 3.9357804939334775
RMSD of residue 68 is 3.6305336045262253
RMSD of residue 69 is 3.6393278785693792
RMSD of residue 70 is 4.6579166326993775
RMSD of residue 71 is 5.824209497298724
RMSD of residue 72 is 8.313547890863301
RMSD of residue 73 is 10.103503158798924
RMSD of residue 74 is 11.462476714893624
RMSD of residue 75 is 12.179220096196657
RMSD of residue 76 is 16.768637539427957
Average rmsd per residue: 4.424080942860908
(input) 64 %
```

X	Main slave	263.40
---	------------	--------